

QUICK GUIDE

Short codes for activating
network services.

How to use the codes: open the Phone app, dial the
indicated code, and press the call button.



Quick guide

1. SHORT CODES FOR ACTIVATING NETWORK SERVICES

PIN CODE AND PWD

PIN	
Change PIN	**04currentPIN*newPIN*newPIN#

PWD	
Change PWD Red	**03*330*currentPWD*newPWD*newPWD#

PWD per defecte: 0000.
Es recomana no utilitzar com a PWD les claus 111 ni 1234.

ACTIVATION AND CALL FORWARDING TO VOICEMAIL

Short voicemail number
242

Long voicemail number
+34633242242

Voicemail is compatible with the missed call notification service, although in the latter case, with some exceptions.

UNCONDITIONAL CALL FORWARDING	
Activate Activate voicemail forwarding Deactivate Check status	*21forwarding number# *21*242# #21# *#21#

CALL FORWARDING WHEN BUSY	
Activate Activate voicemail forwarding Deactivate Check status	*67forwarding number# *67*242# #67# *#67#

This voicemail forwarding service does not allow you to activate the missed call notification option.

CALL FORWARDING IF THERE IS NO ANSWER	
Activate Activate voicemail forwarding Deactivate Check status	*61forwarding number# *61*242# #61# *#61#

CALL FORWARDING IF UNREACHABLE	
Activate Activate voicemail forwarding Deactivate Check status	*62forwarding number# *61*242# #62# *#62#

This voicemail forwarding service does not allow you to activate the missed call notification option.

Quick guide

CALL WAITING

CALL WAITING	
Activate	*43#
Deactivate	#43#
Check status	*#43#

MISSED CALL NOTIFICATION

Short number for the missed call notification service

556

Long number for the service
+34633633556

MISSED CALL NOTIFICATION WHEN BUSY	
Activate	*67*556#
Deactivate	#67#
Check status	*#67#

MISSED CALL NOTIFICATION WHEN UNREACHABLE WITHOUT VOICEMAIL	
Activate	*62*556#
Deactivate	#62#
Check status	*#62#

These notification services are not compatible if voicemail has been activated for the same call forwarding scenarios.

OUTGOING CALL BARRING

INCOMING CALL BARRING	
Activate	*35*PWD#
Deactivate	#35*PWD#
Check status	*#35#

OUTGOING CALL BARRING	
Activate	*33*PWD#
Deactivate	#33*PWD#
Check status	*#33#

INTERNATIONAL CALL BARRING	
Activate	*331*PWD#
Deactivate	#331*PWD#
Check status	*#331#

OTHER SERVICES

CALL WITH HIDDEN NUMBER	
Always activate	*31#
Activate once	#31#number to call
Deactivate	
Check status	*#31#

RINGTONE	
Extend the ringing time	**61*242**ringing time in seconds#